

LINE Notification Setting Flow

Notification of LiteNetics alerts can be sent via LINE, notifying system administrators in real time.

Create LINE business account

Go to,

https://account.line.biz/login?redirectUri=https%3A%2F%2Fmanager.line.biz%2F%3Fstatus%3Dsuccess%26 status%3Dcancelled%26status%3Dcancelled

To create a new account using LINE Official Account Manager via web browsers:

- 1. Go to the above URL.
- 2. Log in with LINE or business account.
- 3. Click "Create LINE official account".
- 4. Fill in the required fields, and choose Continue.
- 5. On the check application page, select Submit.


To create a new account via LINE Official Account APP:

- 1. Tap Log in or sign up with LINE, or Log in or sign up by email.
- 2. Tap "Create LINE official account".

Note: If you already have an account, tap the menu icon at the top left of the screen > Create new.

- 3. Fill in the required fields, and tap Continue.
- 4. Tap "Create account".

Create LINE official account is at the top left of the screen > Create new.



Fill in the required fields, and choose Continue.

Create a LINE o	fficial account	Required
Login info		
Username	Maggie Log out	
Service region	台灣 You'll be able to select from paid plans for 台灣.	
Account info		
Account name •	LiteNetics	10 /20
	This name will appear on the LINE friend list and chat screen.	
Email address •		22 /200
Company or owner's country or region ● ②		
	This country/region info will be displayed where users can see, such as on your account profile.	
Company name		0 /100


LINE notification setting

After creating a LINE business account, then go to **LINE developers** to set up messaging API. Go to https://developers.line.biz/console/


1. Choose to log in with LINE account or business account




2. Click "Create a new provider", enter Provider name and click "Create".



3. You can go to TOP > Your Notification > Roles to create several accounts to manage your notification.




4. Go to TOP > Your Notification > Channels, and then select "Create a Message API channel".



5. Select "Messaging API" in Channel type and "Your Notification" in Provider.




6. Click "Create" and "OK" after reading the following Messaging API Channel details.



7. Go to TOP > LiteNetics > LiteNetics > Messaging API


Click "Messaging API" and go to Channel access token, then click "issue" button to generate access token.




Webhook settings

The URL of endpoint in LiteNetics server that can process webhook events sent by the LINE platform. Note: To verify that the URL works or not, users have to complete "LINE Bot Settings" in LiteNetics first.


1. Back to **LINE Official Account Manager** platform, go to *Chats > Response settings*, disable Auto-Response but enable Webhooks.



2. Input the Webhook URL.




3. To make sure LINE can receive messages sent by LiteNetics, please click "Verify" to make sure LiteNetics server can process the internet.




Greeting Message

After setting up the official channel, you can go to https://account.line.biz/login to set up greeting message content.




LiteNetics Configuration

After creating a LINE business account and set up a developer channel, go back to *LiteNetics admin portal*System > LINE Settings, fill in Bot ID / Channel Secret / Channel Access Token according to LINE developers.



Upload QR code which is generated by LINE, other users can join the channel by this QR code in order to receive alerts sent by server via LINE.




After that, scan the QR code to check whether the new LINE official account is good or not. If good, users will be added to the official LINE account successfully. Please input "your account in LiteNetics" to register a new member. As you can see the message "You already registered for LiteNetics LINE BOT", you can receive alert messages from LiteNetics.



Go to **System > LINE Settings > LINE Bot Test**, input and send a test message, the group member of LINE alert notification will receive the message.

System / LINE Settings



Log in by manager and will see LINE QR code in *Account > User Profile*.

Users can scan this QR code and click "Register" in the LINE message to subscribe to this alert channel.

